

# Chapter 7.

## Energy and energy transfer Energy of a system

- A new approach in Solving the mechanic motion, without using Newton's laws.
- An important concept: conservation of energy.
- Identifying "system".

In this system, All object obey "energy conservation"

### Work :





Fig 7-2.

How effective the force is moving the object?

- ① The magnitude of the force
- ② The direction of the force

$W \equiv F \Delta r \cos \theta$  definition of work.

The work done not only depends the magnitude of the force but also the angle and the displacement of the work.



From the definition

- ① The gravitational force doesn't do work
- ② The Normal force does not do work.

$$W \equiv F \text{ or } \cos \theta$$

$$= \vec{F} \cdot \vec{r}$$


The sign of work depends on the direction of  $\vec{r}$

"+" : the same as the force

"-" , opposite to the force.

Mathematics scalar product.

$$\vec{A} \cdot \vec{B} = AB \cos \theta, \quad \theta \equiv \text{the angle between } \vec{A} \text{ and } \vec{B}$$



(1) The projection of  $\vec{B}$  along the  $\vec{A}$  direction

(2) The scalar product  $\vec{A} \cdot \vec{B}$  is NOT a vector

$$\vec{A} \cdot \vec{B} = \vec{B} \cdot \vec{A}$$

$$\vec{A} \cdot (\vec{B} + \vec{C}) = \vec{A} \cdot \vec{B} + \vec{A} \cdot \vec{C}$$

Unit vectors  $\hat{i}, \hat{j}, \hat{k}$  in a right-handed coordinate system.

$$\hat{i} \cdot \hat{i} = \hat{j} \cdot \hat{j} = \hat{k} \cdot \hat{k} = 1$$

$$\hat{i} \cdot \hat{j} = \hat{i} \cdot \hat{k} = \hat{k} \cdot \hat{i} = 0 \quad \text{— orthogonal}$$

Any vector in this coordinate system can be decomposed into 3 components along the three unit vector system.

$$\vec{A} = A_x \hat{i} + A_y \hat{j} + A_z \hat{k}$$

$$\vec{B} = B_x \hat{i} + B_y \hat{j} + B_z \hat{k}$$

$$\vec{A} \cdot \vec{B} = A_x B_x + A_y B_y + A_z B_z$$

$$\vec{A} \cdot \vec{A} = A_x^2 + A_y^2 + A_z^2 = A^2$$

## Work done by a varying force

$$W = F_x \Delta x$$


$$\approx \sum_{x_i}^{x_f} F_x \Delta x$$

$$= F_{x_1} \Delta x_1 + F_{x_2} \Delta x_2$$

$$= \lim_{\Delta x \rightarrow 0} \sum_{x_i}^{x_f} F_x \Delta x$$

$$= \int_{x_i}^{x_f} F_x dx$$

$$= W = \text{the area under the curve.}$$



for more than one force acting on the system (or, particle)

$$\Sigma W = W_{\text{total}} = \int_{x_i}^{x_f} (\Sigma F_x) dx$$

Example: work done by a spring-block system

$$F_x = -kx$$


↑  
Spring constant

Slope of the force

$$W_s = \int_{x_i}^{x_f} F_s dx$$

$$= \int_{-x_{\text{max}}}^0 (-kx) dx$$


$$= \left[ \frac{1}{2} kx^2 \right]_{-x_{\text{max}}}^0 = \frac{1}{2} kx_{\text{max}}^2$$



maximum work that can be done  
by the force at  $x_{\text{max}}$  displacement.

in general

$$W_s = \int_{x_i}^{x_f} (-kx) dx = \frac{1}{2} kx_i^2 - \frac{1}{2} kx_f^2$$



$$W_{app} = \int_0^{x_{max}} F_{app} \cdot dx$$

$$= \int_0^{x_{max}} kx dx = \frac{1}{2} kx_{max}^2$$

$$W_{app} = \int_{x_i}^{x_f} F_{app} dx = \int_{x_i}^{x_f} kx dx = \frac{1}{2} kx_f^2 - \frac{1}{2} kx_i^2$$

Note  $W_{app} = -W_s$

work as the mechanism of transferring energy into a system

- {: change the speed.
- {: change the temperature
- {: ...

## Kinetic energy

$$\Sigma W = \int_{x_i}^{x_f} \Sigma F dx$$


$$= \int_{x_i}^{x_f} ma dx$$

$$= \int_{x_i}^{x_f} m \frac{dv}{dt} dx = \int_{x_i}^{x_f} m \frac{dv}{dx} \frac{dx}{dt} dx$$

$$= \int_{v_i}^{v_f} m v dv$$

$$= \frac{1}{2} m v_f^2 - \frac{1}{2} m v_i^2$$

$\underbrace{\hspace{2em}}_{E_{Kf.}} \quad \underbrace{\hspace{2em}}_{E_{Ki.}}$




— Work done by force,  $\Sigma F$ , results in a change in the velocity that change the energy  
 $\rightarrow$  kinetic energy

$$K \equiv \frac{1}{2}mv^2$$

$$\therefore \Sigma W = K_f - K_i = \Delta K$$

- Work-Kinetic energy Theorem

→ Non isolated system : the system interact with its environment



The block slow down (Kinetic energy decreases)  
The rest of the energy transferred to the surface  
as heat (internal energy)

$$(\Sigma F_x) \Delta x = (ma_x) \Delta x$$

- Newton's 2<sup>nd</sup> law

$$a_x = \frac{v_f - v_i}{t}, \Delta x = \frac{1}{2}(v_i + v_f)t$$

$v = v_0 + at$

- A particle under constant acceleration.

$$\therefore (\Sigma F_x) \Delta x = m \left( \frac{v_f - v_i}{t} \right) \frac{1}{2}(v_i + v_f)t$$

$$(\Sigma F_x) \Delta x = \frac{1}{2}mv_f^2 - \frac{1}{2}mv_i^2$$

↑  
The displacement of the large object (not the point)

$$= (-f_k) \Delta x = \frac{1}{2}mv_f^2 - \frac{1}{2}mv_i^2$$
$$= \Delta K$$

$$\therefore -f_k d = \Delta K$$

$$\therefore \Delta K = -f_k d + \Sigma W_{\text{other forces}}$$

$$\Delta E_{\text{system}} = \Sigma T = \Delta K + \Delta \bar{E}_{\text{int}} = 0$$

Conservation of energy

$$-f_k d + \Delta \bar{E}_{\text{int}} = 0 \rightarrow \Delta \bar{E}_{\text{int}} = f_k d$$

The result of a friction force is to transform kinetic energy into internal energy, and the increase in internal energy is equal to the decrease in kinetic energy.

Power

$$\bar{P} \equiv \frac{W}{\Delta t} = \lim_{\Delta t \rightarrow 0} \frac{W}{\Delta t} = \frac{dW}{dt}$$

$$= \vec{F} \cdot \frac{d\vec{r}}{dt}$$

$$= \vec{F} \cdot \vec{v}$$

$$\equiv \frac{dE}{dt} \quad \text{energy transfer}$$

$$1 \text{ W} = 1 \text{ J/sec} = 1 \text{ kg} \cdot \text{m}^2 / \text{s}^3$$

$$1 \text{ hp} = 746 \text{ W}$$